

后台接入说明

以下是简单说明业务后台接入过程需要实现的逻辑：

- 1、业务后台生成客户端推流所需要的user信息， `roomID` ， `streamID` 等，且保证各信息全局唯一，客户端在推流之前，下发给客户端。
- 2、客户端推流成功后，业务后台可以接收ZEGO后台的 流创建回调，用来增加直播列表（可维护直播列表）。备注：流创建回调里面的pic_url可用于鉴黄，默认20s一张的缓存图片；pic_url只能在推流过程中使用，推流结束后无效。
- 3、客户端停止推流后，业务后台可以接收ZEGO后台的 流关闭回调，用来删除直播列表（可维护直播列表）。
- 4、客户端结束直播后，业务后台可以接收ZEGO后台的 录制文件生成回调，用来做点播文件。
- 5、如需要配置回调信息，请登录[即构管理控制台](#)自主配置。

The screenshot displays a management console interface with two main sections: '基本信息' (Basic Information) and '高级设置' (Advanced Settings). The '高级设置' section is expanded to show '测试环境' (Test Environment) settings. A red box highlights three callback configuration fields: '流创建' (Stream Create) with URL 'http://xxxxxx(domain)/create', '流关闭' (Stream Close) with URL 'http://xxxxxx(domain)/close', and '录制文件获取' (Recording File Retrieval) with URL 'http://xxxxxx(domain)/playback'. Each field has a minus sign icon to its right. Below these fields are buttons for '+ 添加后台回调' (Add Backend Callback) and '接口文档' (API Documentation). The '基本信息' section includes buttons for '申请上线' (Apply for Online), '延长测试期限' (Extend Test Period), and '编辑' (Edit). A table below shows details for the current environment: '测试环境' (Test Environment), '仅限大陆' (Mainland Only), '2020-05-09' (Valid Time), and links for '查看' (View) for AppSign, Environment Config, and Backend Keys.

项目	AppId	环境类型	业务地区	有效时间	AppSign	环境配置	后台相关密钥
	■■■	测试环境	仅限大陆	2020-05-09	查看	查看	查看